

Mind Open Source Project

MosP Verion3環境
インストール手順
勤怠管理
Linux版MySQL対応

平成21年12月8日

株式会社マインド

0. CENTOS5 インストール

ユーザー「usermosp」を作成する。

デフォルトの状態から、次のパッケージグループを追加する。

- ・MySQL データベース
- ・Web サーバー
- ・サーバー設定ツール
- ・システムツール

以下のコマンドは、root ユーザーで実行する。

1.mysql 初期設定

```
# mkdir /var/lib/mysql/innodb  
# mkdir /var/lib/mysql/innolog  
  
# vi /etc/my.cnf
```

以下のファイルが開かれる。

```
[mysqld]  
datadir=/var/lib/mysql  
socket=/var/lib/mysql/mysql.sock  
# Default to using old password format for compatibility with mysql 3.x  
# clients (those using the mysqlclient10 compatibility package).  
old_passwords=1
```

```
[mysql.server]  
user=mysql  
basedir=/var/lib
```

```
[mysqld_safe]
log-error=/var/log/mysqld.log
pid-file=/var/run/mysqld/mysqld.pid
----
```

これを、次のように変更。

```
-----
[client]
port = 3306
socket = /var/lib/mysql/mysql.sock
default-character-set = cp932
```

```
[mysqld]
port = 3306
socket = /var/lib/mysql/mysql.sock
skip-locking
key_buffer = 16M
max_allowed_packet = 2M
table_cache = 64
sort_buffer_size = 1M
net_buffer_length = 32K
read_buffer_size = 512K
read_rnd_buffer_size = 1M
myisam_sort_buffer_size = 8M
default-character-set = cp932
default-table-type = InnoDB
```

```
log-bin=mysql-bin
server-id = 1

innodb_data_home_dir = /var/lib/mysql/innodb
innodb_data_file_path=ibdata1: 512M:autoextend
innodb_buffer_pool_size = 32M
innodb_additional_mem_pool_size = 8M
innodb_log_group_home_dir = /var/lib/mysql/innolog
innodb_log_file_size=256M
innodb_log_buffer_size = 4M
```

```
innodb_flush_log_at_trx_commit = 1  
innodb_lock_wait_timeout = 50
```

```
[mysqldump]  
quick  
max_allowed_packet = 32M  
default-character-set = cp932
```

```
[mysql]  
no-auto-rehash  
default-character-set = cp932
```

```
[mysql.server]  
user=mysql  
basedir=/var/lib
```

```
[mysqld_safe]  
log-error=/var/log/mysqld.log  
pid-file=/var/run/mysqld/mysqld.pid  
----
```

```
# service mysqld start
```

以下のメッセージが表示される。

```
----  
MySQL データベースを初期化中: Installing all prepared tables  
Fill help tables
```

To start mysqld at boot time you have to copy support-files/mysql.server
to the right place for your system

Pkintai REMEMBER TO SET A PASSWORD FOR THE MySQL root USER !

To do so, start the server, then issue the following commands:

```
/usr/bin/mysqladmin -u root password 'new-password'  
/usr/bin/mysqladmin -u root -h localhost.localdomain password 'new-password'  
See the manual for more instructions.
```

You can start the MySQL daemon with:

```
cd /usr ; /usr/bin/mysqld_safe &
```

You can test the MySQL daemon with the benchmarks in the 'sql-bench' directory:

```
cd sql-bench ; perl run-all-tests
```

Please report any problems with the /usr/bin/mysqlbug script!

The latest information about MySQL is available on the web at

<http://www.mysql.com>

Support MySQL by buying support/licenses at <http://shop.mysql.com>

[OK]

MySQL を起動中:

[OK]

```
# /usr/bin/mysqladmin -u root password root
```

```
# chkconfig mysqld on
```

```
# /usr/bin/mysql -u root -p
```

データベース kintai を作成

```
> drop database test;
```

```
> create database kintai character set cp932;
```

MySQL ユーザーusermosp を作成

```
> GRANT insert,update,delete,select,lock tables ON *.* TO usermosp@localhost IDENTIFIED BY 'passmosp'  
WITH GRANT OPTION;
```

```
> quit
```

MySQL ユーザーusermosp のパスワード passmosp を設定

kintai3WEB-INF0-kintai3-extra.properties ファイルを変更する

MySQL の部分のコメントアウトを解除し、PostgreSQL の部分を削除又はコメントアウトする。

```
<?xml version="1.0" encoding="Windows-31J"?>  
<!DOCTYPE properties SYSTEM "http://java.sun.com/dtd/properties.dtd">  
<!--  
MosP - Mind Open Source Project http://www.mosp.jp/
```

This program is free software; you can redistribute it and/or modify it under the terms of the GNU General Public License as published by the Free Software Foundation; either version 2 of the License, or (at your option) any later version.

This program is distributed in the hope that it will be useful, but WITHOUT ANY WARRANTY; without even the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR PURPOSE. See the GNU General Public License for more details.

You should have received a copy of the GNU General Public License along with this program; if not, write to the Free Software Foundation, Inc., 59 Temple Place - Suite 330, Boston, MA 02111-1307, USA.

-->

<properties>

```

<!-- ASP 設定(0 : ASP(x ユーザー:1 アプリ)、1:ASP(1 ユーザー:1 アプリ)、2 : 非 ASP) -->
<entry key="asp.flag">2</entry>

<!-- MySQL -->
<!-- <entry key="asp.dbdriver">org.gjt.mm.mysql.Driver</entry> -->
<!--
key="asp.dburl">jdbc:mysql://localhost:3306/kintai?useUnicode=true&characterEncoding=MS932&amp;p;zeroDateTimeBehavior=convertToNull</entry> -->
<!-- <entry key="asp.dbuser">usermosp</entry> --> DB ユーザ名
<!-- <entry key="asp.dbpass">passmosp</entry> --> DB ユーザーパスワード
<!-- PostgreSQL -->
<entry key="asp.dbdriver">org.postgresql.Driver</entry>
<entry key="asp.dburl">jdbc:postgresql://localhost:5432/kintai</entry>
<entry key="asp.dbuser">usermosp</entry>
<entry key="asp.dbpass">passmosp</entry>
<!-- アプリケーションタイトル -->
<entry key="app.title">MosP 勤怠管理</entry>
<!-- アプリケーションバージョン -->
<entry key="app.version">v3.x.x</entry>

```

DB 名

DB ユーザ名

DB ユーザーパスワード

メインメニューのタイトル

```
<!-- リスト表示件数 -->
<entry key="app.list">100</entry>

<!-- パスワード有効期限(日) -->
<entry key="acc.validity"></entry>

<!-- OpenDocument 出力 -->
<entry key="kintai.useodf"></entry>

</properties>
*****以上*****
```

2. java のインストール

「/home/usermosp」に「jdk-1_5_0_16-linux-i586-rpm.bin」を配置する。

```
# cd /home/usermosp
# chmod a+x jdk-1_5_0_16-linux-i586-rpm.bin
# ./jdk-1_5_0_16-linux-i586-rpm.bin
```

ライセンスが表示され、次のように聞かれる。

```
-----
Do you agree to the above license terms? [yes or no]
```

「yes」と入力して Enter。

展開される。

```
# rm -rf jdk-1_5_0_16-linux-i586-rpm.bin
```

3. tomcat のインストール

「/home/usermosp」に「apache-tomcat-5.5.26.tar.gz」を配置する。

```
# cd /home/usermosp  
  
# tar zxvf apache-tomcat-5.5.26.tar.gz  
  
# mv apache-tomcat-5.5.26 /usr/local/tomcat  
  
# rm -rf apache-tomcat-5.5.26.tar.gz  
  
# vi /etc/rc.d/init.d/tomcat
```

以下の内容を記載して保存

```
----  
#!/bin/bash  
  
export LANG=ja_JP.UTF8  
export JAVA_HOME=/usr/java/jdk1.5.0_16  
export CATALINA_HOME=/usr/local/tomcat  
export CATALINA_OPTS="-server -Xmx64M -Xms32M -Xss256k -Djava.awt.headless=true"  
  
start(){  
    $CATALINA_HOME/bin/startup.sh  
}  
  
stop(){  
    $CATALINA_HOME/bin/shutdown.sh  
}  
  
case "$1" in  
    start)  
        start  
        ;;  
    stop)  
        stop  
    esac
```

```
;;
restart)
    stop
    start
;;
status)
    $CATALINA_HOME/bin/catalina.sh version
;;
*)
    echo "Usage: $0 {start|stop|restart|status}"
esac

exit 0
-----
# chmod +x /etc/rc.d/init.d/tomcat

# cd /etc/rc.d/rc0.d
# ln -s ../init.d/tomcat K99-tomcat
# cd /etc/rc.d/rc1.d
# ln -s ../init.d/tomcat K99-tomcat
# cd /etc/rc.d/rc6.d
# ln -s ../init.d/tomcat K99-tomcat
# cd /etc/rc.d/rc2.d
# ln -s ../init.d/tomcat S70-tomcat
# cd /etc/rc.d/rc3.d
# ln -s ../init.d/tomcat S70-tomcat
# cd /etc/rc.d/rc4.d
# ln -s ../init.d/tomcat S70-tomcat
# cd /etc/rc.d/rc5.d
# ln -s ../init.d/tomcat S70-tomcat

# /etc/rc.d/init.d/tomcat start
```

4.apache-tomcat 連携

```
# vi /etc/httpd/conf.d/proxy_ajp.conf
```

次の記述を加える。

```
----  
ProxyPass /kintai3/srv/ ajp://localhost:8009/kintai3/srv/  
ProxyPass /kintai3/pub/ ajp://localhost:8009/kintai3/pub/  
----
```

```
# vi /usr/local/tomcat/conf/server.xml
```

次の記述をコメントアウト(<!-- -->)


```
----  
<Connector port="8080" maxHttpHeaderSize="8192"  
          maxThreads="150" minSpareThreads="25" maxSpareThreads="75"  
          enableLookups="false" redirectPort="8443" acceptCount="100"  
          connectionTimeout="20000" disableUploadTimeout="true" />  
----
```

```
# vi /etc/httpd/conf/httpd.conf
```

次の箇所を変更する。

```
----  
AddDefaultCharset UTF-8  
  
# AddDefaultCharset UTF-8  
AddDefaultCharset shift-jis  
  
----  
  
# chkconfig httpd on
```


Mind Open Source Project



オープンソースソフトウェアに携わる世界中の開発者の皆様に感謝しております。

注意事項

文中に引用された社名 / 製品名 / サービス名 / ロゴについては、各々の会社の商標ないしは登録商標であり、各所有者が商標権を保持しています。株式会社マインドは本書に含まれる情報を予告なく変更することがありますのでご了承ください。本書の内容変更については、隨時、文末のお問合せ先までお問い合わせください。

= お問い合わせ先 =

株式会社マインド セールス&マーケティング戦略部 宛

E-Mail: sales@e-mind.co.jp

TEL: 044-272-9093 FAX: 044-272-9094

(受け付け時間: 平日9時 ~ 17時まで)

〒210-0005 神奈川県川崎市川崎区東田町6 - 2 ミヤダイビル8F

URL: <http://www.e-mind.co.jp>